the BEADSMITH
Inspiration Squad

Isabella Lam
New Thinking with Endless Possibilities

LILY Necklace

MATERIAL LIST

2 grams Miyuki Round Seed Beads size 8/0 **R8**

2 grams Miyuki Round Seed Beads size 11/0 **R11**

2 grams Miyuki Round Seed Beads size 15/0 **R15**

38 CzechMate tile Beads **CT**

37 CzechMate Lily Petals Beads **LP**

37 MiniDuo two hole beads **MD**

Magnetic clasp

Fireline 6lb or similar

12# beading needle

BASIC

Starting your work:

Start with a comfortable thread length. I recommend about 5 feet (about 1.50 meter) for starting.
String a stopper bead leaving about 4" (10 cm) tail. Go through the stopper bead twice to anchor the bead. (Stopper bead is an 11/0 round seed beads different color from those you are working with. This bead you will remove at the end of your work or if mentioned otherwise).

Don't Forget:

Never use the same thread you worked in your beading project to attach the clasp. Use a new thread. This will assure and allow you to replace the clasp in case in got broken or extend your work, without losing your work.

Adding Thread:

Usually I think it is best to knot the new thread into the work a few beads before the end of the thread. The knot should be between two beads and then continue through the beads that the old thread is coming out of. Only then finish the old thread.

Isabella Lam
New Thinking with Endless Possibilities

Finishing Added Thread:

Never cut the thread near the knot point. The knot point is a weak point and can be opened. After attaching the new thread between two beads with double knot, I recommend to take the short tail left and pass it back through the beads (at least 2 inches) before cutting.

STEP 1

Pick up 1xR8, 1xCT, 1xR11, 1xR8, 1xR11. Go up through the free hole of the CT.

STEP 2

Pick up 1xR15, 1xR11, 1xMD, 1xR11, 1xR15, 1xCT, 1xR11, 1xR8, 1xR11. Go up through the free hole of the CT.

Repeat this step until you reach your desired length.

## STEP 3

At the ends finish pointing out from the last CT.

STEP 4

Pick up 1xR8. Go back through the CT, R11, R8, and R11.

STEP 5

Pick up 1xR11, 1xLP, 1xR11. Go through the next R11, R8, and R11. Repeat this step all over the necklace.

STEP 6

At the ends go up through the last CT. Pick up 1xR8. Go back tough the CT, R11, R8, R11.

## STEP 7

Pick up 6xR15. Go through the free hole of the MD.

STEP 8

Pick up 6xR15. Go through the next R11, R8, and R11.

.

STEP 9

Repeat steps 7 – 8 all over the necklace.

STEP 10

Attach new thread about 10 inch/25 cm. Locate your needle point out from the last R8 on top of the last CT. Pick up 2xR11, clasp, 2xR11. Close to a circle on the R8 you began this step. Go through all to inforce the thread and finish the thread.

Repeat this step on the other side of the necklace too.

Knot point

Enjoy your Beading!

For more Jewelry Patterns & Kits, beading supply please visit my shops:
http://www.etsy.com/shop/bead4me
http://www.isabellalam.com

www.beadsmith.com